Graveley Lab shRNA knockdown followed by RNA-seq Biosample Preparation and Characterization Document

Wet Lab: Sara Olson and Lijun Zhan Computational Lab: Xintao Wei PI: Brenton Graveley

Department of Genetics and Genome Sciences UConn Institute for Systems Genomics UConn Health 400 Farmington Avenue Farmington, CT 06030 USA

October 17, 2018

Project: ENCORE Grant: U41HG009889 Sample Description: shRNA Knockdown of XPO1 in K562 cells Cell Line: K562 RNA ID: XPO1-BGKLV38-120C ENCODE BIOSAMPLE ACCESSION: ENCBS885KEV

This document contains the protocols used to generate shRNA expressing lentiviral particles, transduction of K562 cells, harvesting of RNA, characterization of the RNA integrity and measurement of target knockdown efficiency by both qRT-PCR and Western blotting.

Protocol for producing shRNA lentiviral particles

In this portion of the protocol we will generate lentiviral particles expressing either an shRNA targeting an RNA binding protein mRNA or a non-target control shRNA.

| Item | Info |
|-----------------|-----------------------|
| Target | XPO1-human |
| shRNA Source | The RNAi Consortium |
| Product ID | TRCN0000153235 |
| Target sequence | GCTCAAGAAGTACTGACACAT |
| Vector backbone | pLKO.1 |




Figure 1: Schematic depiction of backbone of the pLKO.1 plasmid encoding the shRNA.

Day 1

- Plate 0.8-1x10⁶ 293 T cells (catalog number: CRL-11268, ATCC) in each well of 6-well plate with 10 % FBS (catalog number: 30-2020, ATCC) DMEM (catalog number: 11995-065, Life technologies) medium without penicillin and streptomycin.
- 2. Incubate overnight. Cells should be 70-80% confluent.

Day 2

1. In polypropylene tubes, make a cocktail for each transfection as follows:

| Reagent | Quantity |
|----------------------|----------------|
| pLKO-shRNA | 500 ng |
| psPAX2 Packaging DNA | 500 ng |
| PMD2.G Envelope DNA | 50 ng |
| serum-free OPTI-MEM | to 100 μl |

- 2. Add 3.1 μ l of FuGENE HD Transfection reagent (Catalog number: E2311, Promega) to the tube (FuGENE:DNA=3:1)
- 3. Incubate for 20 minutes at room temperature.
- 4. Gently add the DNA mix dropwise to cells.
- 5. Incubate the cells at $37\,^{\rm o}{\rm C}$ for 12-15 hr.

Day 3

1. In the morning, change the media to remove the transfection reagent, wash with PBS once and add 1.5 ml fresh media +10% FBS + penicillin/streptomycin.

Day 4

- 1. Harvest media from cells, store at $4\,^{\circ}\mathrm{C}.$
- 2. Add 1.5 ml fresh media.

Day 5

- 1. Harvest the media from the cells and pool with the media collected on Day 4.
- 2. Spin the media at 1250 rpm for 5 min to remove cells.
- 3. Freeze the virus stock at $-40\,^{\circ}\mathrm{C}.$

qPCR Lentivirus Titration Assay

Lentiviral titrations are performed using the qPCR Lentivirus Titration kit from Applied Biological Materals Inc. (Catalog Number LV900).

- 1. Add 2 μ l of the viral supernatant to 18 μ l of Virus Lysis buffer and incubate at RT for 3 mins. This is now referred to as viral lysate.
- 2. qRT-PCR set up:

| Component | Viral lysate | Positive Control | Positive Control | Negative control |
|-------------------|----------------|------------------|------------------|------------------|
| | | (STD1) | (STD2) | (NTC) |
| 2x qPCR Mastermix | $12.5 \ \mu l$ | $12.5 \ \mu l$ | $12.5 \ \mu l$ | $12.5 \ \mu l$ |
| Viral Lysate | $2.5 \ \mu l$ | | | |
| STD1 | | $2.5 \ \mu l$ | | |
| STD2 | | | $2.5 \ \mu l$ | |
| Reagent-mix | $10 \ \mu l$ | $10 \ \mu l$ | $10 \ \mu l$ | 10 µl |
| Final vol. | $25 \ \mu l$ | $25 \ \mu l$ | $25 \ \mu l$ | $25 \ \mu l$ |

3. qRT-PCR program:

| STEP | TEMP | TIME |
|-----------------------|------------------------|------------|
| Reverse Transcription | 42 °C | 20 minutes |
| Enzyme Activation | $95^{\circ}\mathrm{C}$ | 10 minutes |
| 40 Cycles | $95^{\circ}\mathrm{C}$ | 15 seconds |
| | $60^{\circ}\mathrm{C}$ | 1 minute |

4. Calculate the titer from Ct values by using abm's on-line lentiviral titer calculator at http://www.abmgood.com/High-Titer-Lentivirus-Calculation.html or by using the formula: IU/ml=Dilution factor x 5x10^7/2^3(Ct sample-Ct STD1)/(CtSTD2-CtSTD1)

Lentiviral Transduction Protocol

For K562 cells

Source: ATCC CCL-243 (lot 59300853)

Growth Media for K562 cells:

500 ml RPMI-1640 with glutamine medium (Hyclone, SH30027.01)
50 ml Fetal Bovine Serum (FBS) (10% Final Concentration) (Hyclone, SH30071.03)
5 ml Pen-Strep (1% Final Concentration) (Invitrogen, 15140-163)

Culturing

- 1. Remove a frozen stock vial of K562 cells from liquid nitrogen.
- 2. Thaw it in a 37 $^{\circ}\mathrm{C}$ water bath.
- 3. As soon as it thawed, transfer the cells into the growth medium.
- 4. Centrifuge at 1000 rpm for 5 minutes.
- 5. Resuspend the cells in the growth medium such that the final cell density is about $1x10^{5}$ cells/ml.
- 6. Split the cells every 2 to 3 days.
- 7. Grow the cells to required numbers.

Prepare cells for transduction

Day 0

- 1. Plate 5-7x10⁵ cells in each well of 12-well plates.
- 2. Add 8 $\mu \rm g/ml$ of polybrene (Catalog Number H9268, Sigma-Aldrich) to the cells.
- 3. Add lentiviral particles (MOI ~ 10) to appropriate wells.

Day 1

1. After 24 hrs, change to fresh media (2 ml) with 3 μ g/ml of puromycin.

Day 3

1. Change to fresh media (2 ml) with 3 μ g/ml of puromycin.

Day 5

1. Change to fresh media (2 ml) with 3 μ g/ml of puromycin.

Day 6

1. Harvest half of the cells to prepare RNA and half of the cells to prepare a protein lysate for western blotting.

RNA Isolation

RNA isolation is performed using a Promega Maxwell (R)16 Instrument and the Maxwell (R)16 LEV simply RNA Cells Kits (Catlog Number AS1270).

- 1. Pellet cells at 300 x g for 3 minutes and remove medium.
- 2. Add 200 μ l of chilled 1-Thioglycerol/Homogenization solution to the cell pellet and vortex until the pellet is dispersed.
- 3. Add 200 μ l of lysis buffer and votex vigorously for 15 sec to mix.
- 4. Transfer all 400 μl lysate to well 1 of the Maxwell 16 LEV cartridge.
- 5. Add 5 μ l of DNase I solution to well 4 of the cartridge.
- 6. Put elution tubes with 40-50 μl of nuclease-free water and LEV plungers in the cartridge.
- 7. Transfer the Maxwell 16 LEV cartridge rack containing prepared cartridges on the Maxwell 16 Instrument.
- 8. Push Run/Stop button to start run.

RNA Quality Control

The quality of the RNA is measured using an Agilent TapeStation Instrument with the RNA screen tape (Catlog Number 5067-5576).




Figure 2: Agilent TapeStation image of 1 μl of total RNA sample.

qRT-PCR Assay to Monitor mRNA Target Knockdown Efficiency

cDNA Synthesis

This assay uses the iScript cDNA Synthsis Kit from BIO-RAD (Catalog number: 170-8891)

1. Reaction Setup:

| Reagent | Quantity |
|---------------------------------|-------------------------------|
| 5x iScript reaction mix | $2 \mu l$ |
| iScript reverse transcriptase | $0.5 \ \mu l$ |
| Nuclease-free water | $\mathbf{x} \ \mu \mathbf{l}$ |
| RNA template (200 ng) | $\mathbf{x} \ \mu \mathbf{l}$ |
| Total volume | $10 \ \mu l$ |

2. Reaction Protocol:

| Time | Temperature |
|------------|-------------|
| 5 minutes | 25 °C |
| 30 minutes | 42 °C |
| 5 minutes | 85 °C |
| Hold | 4°C |

qPCR Assay

This assay uses Phusion High-Fidelity DNA Polymerase from NEB (Catalog number: M0530L) and SYBR Green from Invitrogen (Catalog number: S7563)

1. Reaction setup:

| Reagent | Quantity |
|----------------------------------|---------------|
| 5X Phusion HF Buffer | $4 \ \mu l$ |
| 10 mM dNTPs | $0.4 \ \mu l$ |
| $10 \ \mu M$ Forward Primer | $1 \ \mu l$ |
| $10 \ \mu M$ Reverse Primer | $1 \ \mu l$ |
| Template (1:20 of cDNA reaction) | $1 \ \mu l$ |
| Phusion DNA Polymerase | $0.2 \ \mu l$ |
| SYBR Green $(10,000 \text{ X})$ | $0.1 \ \mu l$ |
| Nuclease-free water | to 20 μl |
| Total volume | $20 \ \mu l$ |

2. Reaction Protocol:

| STEP | TEMP | TIME |
|----------------------|---------------------------|------------|
| Initial Denaturation | 98 °C | 30 seconds |
| 35 Cycles | 98 °C | 10 seconds |
| | $58-66^{\circ}\mathrm{C}$ | 15 seconds |
| | $72^{\circ}\mathrm{C}$ | 10 seconds |

3. Data Analysis:

Data analysis is perfomed using the $2-\Delta\Delta\mathrm{Ct}$ Method.




Figure 3: qRT-PCR analysis of depletion level of the target RNA binding protein in control and knockdown cells. The percent depletion was calculated in the RNA sample isolated from K562s transduced with an shRNA targeting XPO1 (ENCODE Biosample ENCBS885KEV) in comparison to K562 cells transduced with a control non-target shRNA (ENCODE Biosample ENCBS479HRC). The efficiency of depletion is normalized using Tubulin as a control.

Western Blot Assay to Monitor Protein Target Knockdown Efficiency

A western blot is performed to determine the knockdown efficiency of the target RNA binding protein. For this biosample, the following antibodies were used:

RNA binding protein primary antibody: XPO1

Loading control primary antibody: Tubulin

1. Purify protein by resuspending cell pellets in 100 μ l Lysis buffer (50 mM Tris-HCl, pH 7.4; 100 mM NaCl; 1% NP-40; 0.1% SDS; 0.5% sodium deoxycholate) with protease inhibitor (Roche cocktail).

- 2. Vortex vigorously and leave tubes on ice at least 30 min.
- Spin 18,000g, 20 min, 4 °C. Recover the supernatant in a new tube on ice. Discard the pellet.
- 4. Quantitate the protein concentration using the Pierce BCA kit.
- 5. Load $30-60 \ \mu g$ of protein per sample depending on expression levels of the protein of interest in the cell type.
- 6. Dilute the protein samples with 4X sample buffer and 10X reducing agent (Invitrogen NuPage reagents) and heat at 70 °C for 10 min.
- 7. While samples are heating, prepare the gel: 4-12% Bis–Tris gel for proteins 10-220 kDa, or 8% Tris–glycine for proteins over 220 kDa. Dilute MOPS running buffer to 1X and pour into buffer tank. Add 500 μ l of antioxidant to the inner chamber of the buffer tank. Wash out all wells of the gel with buffer.
- 8. Load 3 μ l of Licor Odyssey prestained molecular weight marker (928–4000) and protein samples. Run the gel at 200 V for about an hour, until the dye just runs off the gel (less for small molecular weight proteins).
- 9. Transfer to PVDF for 30 min in transfer buffer, with methanol and antioxidant, using BioRad Semi-dry transfer apparatus.
- 10. After transfer, block membrane in 5-10 mls of Licor Blocking buffer for 1 hour at room temperature.
- 11. Incubate with the RNA binding protein primary antibody $(0.2 \ \mu g/ml)$ and the loading control primary antibody (mfg recommended dilution) diluted in Licor block with 0.1% tween 20 on a rocker at 4 °C overnight.
- 12. The next day, wash the blot 4 x 5 min each in TBST.
- 13. Prepare the secondary antibody (Rockland Fluorescent TrueBlot antirabbit IgG IRDye800 (Catalog number 18-3216-32) for the RBP and Licor IRDye680 secondary antibody for the loading control). Dilute the antibodies according to the mfg instructions in Licor blocking buffer with 0.1% Tween 20 and 0.01% SDS. Incubate on a rocker for 30-60 min, at room temperature.
- 14. Wash 4 x 5 min each in TBST. Rinse 1x in TBS (no T) and scan on the Licor Odyssey instrument.




Figure 4: Western Blot Analysis of depletion level of the target RNA binding protein in control and knockdown cells. Lane 1: Molecular weight marker. Lane 2: 30 μ g of protein from K562 transduced with a control, non-target shRNA (ENCODE Biosample ENCBS479HRC and ENCBS865TCO). Lane 3: 30 μ g of protein from K562 transduced with an shRNA targeting XPO1 (ENCODE Biosample ENCBS186DPZ). Lane 4: 30 μ g of protein from K562 transduced with an shRNA targeting XPO1 (ENCODE Biosample ENCBS186DPZ). Samples were separated by SDS-PAGE, transferred to a membrane and blotted using antibodies against XPO1 (ENCODE Antibody ENCAB085DMF) and Tubulin as controls.